

Install and Set Up SQL

Steps


- 1. Install SQL. (Check compatible versions.)
 - a. Choose New SQL Server stand-alone installation....




- b. Include any product updates.
- c. Accept the defaults in Feature Selection, Instance Configuration, and Server Configuration.
- d. In Database Engine Configuration, under Authentication Mode, choose Mixed Mode.



- e. Accept the defaults in remaining dialogs.
- 2. Create a SQL database for your website.
 - a. In the Microsoft SQL Server Management Studio > Object Explorer, right-click on Databases, and choose New Database....




b. Enter the name of the new database. Click OK.




- c. Note: Remember the database name, because it will be required by the DNN Installation Wizard.
- 3. Create a SQL user account.

Notes:


- Use SQL authentication.
- Turn off the Enforce Password requirement.
- a. Under Security, right-click on Logins, and choose New Login....




b. Enter the username, choose **SQL Server authentication**, add a password, uncheck **Enforce password policy**, and choose the database.




- c. Note: Remember the username and password, because they will be required by the DNN Installation Wizard.
- 4. Give the new SQL user **db owner** access to the new database.
 - a. In **Object Explorer**, under your database > **Security**, right-click on **Users**, and choose **New User...**.




b. Set User type to SQL user with login.



c. Enter the username of the account you just created, then click Check Names.



d. Under Select a page, select Membership, and check the db owner database role membership.



Sources

- <u>Setting up Your Module Development Environment</u>, based on <u>Setting up your DotNetNuke Module Development Environment</u> by Chris Hammond.
- Installing DNN by Clinton Patterson